14. Mail Group Activities

CHK^XMA21

Checks to see if a user is a member of a mail group. If the user is a member, **\$T** is set to "true"; otherwise, it's set to "false".



There is no other equivalent API.

Input Variables:

XMDUZ DUZ of the user in question.

Y IEN of the mail group in the MAIL GROUP file (#3.8).

Output Variables:

\$T

• \$\$DM^XMBGRP(XMGROUP,,XMY,XMQUIET)

Deletes local members from a mail group. Only local members can be deleted with this call. There is no API that deletes any other type of member. Returns 1, if no error; 0 otherwise.



There is no other equivalent API.

Input Parameters:

XMGROUP Mail group IEN or full name (without the **G.**).

.XMY Array of local users to delete from the mail group. Only DUZs are accepted

(names are not).

XMQUIET Silent flag.

=0—interactive. Any errors will be displayed.

=1—silent (default). Any errors will be sent in a message to the Postmaster and

the user (DUZ) making this call.

Parameters Killed Upon Exit:

XMY

• \$\$MG^XMBGRP(XMGROUP,XMTYPE,XMORG,XMSELF,,XMY,,XMDESC,XMQUIET)

Creates a new mail group or adds members to an existing mail group. Only local members can be added with this call. There is no API that adds any other type of member. Returns mail group IEN if no error; 0 otherwise.



There is no other equivalent API.

Input Parameters:

XMGROUP = Mail group name (without the G_{\bullet}), if new mail group.

=Mail group IEN or full name (without the **G.**), if existing mail group.

XMTYPE Type of mail group. Used only for creating a mail group, otherwise it's ignored.

=0—Public (default)

=1—Private

XMORG DUZ of group organizer. Used only for creating a mail group, otherwise it's

ignored.

XMSELF Allow self-enrollment? (0=no; 1=yes) Used only for creating a mail group,

otherwise it's ignored.

.XMY Array of local users to add to the mail group. Only DUZs are accepted (names

are not).

.XMDESC Array of text to put in the description field of the mail group. Used only for

creating a mail group, otherwise it's ignored.

XMQUIET Silent flag.

=0—Interactive. Any errors will be displayed.

=1—Silent (default). Any errors will be sent in a message to the Postmaster and

the user (DUZ) making this call.

Parameters Killed Upon Exit:

XMY